
Chapter 3 Transport Layer



Computer Networking: A Top Down Approach, 6th edition. Jim Kurose, Keith Ross Addison-Wesley, Feb 2012.

Chapter 3: Transport Layer

Our goals:

- understand principles behind transport layer services:
 - o multiplexing/demultiplexing
 - o reliable data transfer
 - flow control
 - congestion control

- □ learn about transport layer protocols in the Internet:
 - UDP: connectionless transport
 - TCP: connection-oriented transport
 - TCP congestion control


Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - o connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
 - send side: breaks app messages into segments, passes to network layer
 - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
 - Internet: TCP and UDP



Transport vs. network layer


- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network layer services

Household analogy:

- 12 kids sending letters to 12 kids
- processes = kids
- app messages = letters in envelopes
- □ hosts = houses
- transport protocol = Ann and Bill
- network-layer protocolpostal service

Internet transport-layer protocols

- reliable, in-order delivery (TCP)
 - congestion control
 - flow control
 - connection setup
- unreliable, unordered delivery: UDP
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees



Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - o segment structure
 - o reliable data transfer
 - flow control
 - o connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Multiplexing/demultiplexing

Demultiplexing at rcv host:


delivering received segments to correct socket

= socket

= process


Multiplexing at send host:

gathering data from multiple sockets, enveloping data with header (later used for demultiplexing)



How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries 1 transport-layer segment
 - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Connectionless demultiplexing

Create sockets with port numbers:

```
DatagramSocket mySocket1 = new
  DatagramSocket(12534);
```


- DatagramSocket mySocket2 = new
 DatagramSocket(12535);
- □ UDP socket identified by two-tuple:

(dest IP address, dest port number)

- When host receives UDP segment:
 - checks destination port number in segment
 - directs UDP segment to socket with that port number
- □ IP datagrams with different source IP addresses and/or source port numbers directed to same socket

Connectionless demux (cont)

DatagramSocket serverSocket = new DatagramSocket (6428);




SP provides "return address"

Connection-oriented demux


- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- receiving host uses all four values to direct segment to appropriate socket

- Server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
 - non-persistent HTTP will have different socket for each request

Connection-oriented demux (cont)



Connection-oriented demux: Threaded Web Server



Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
 - o lost
 - delivered out of order to app

□ connectionless:

- o no handshaking between UDP sender, receiver
- each UDP segment handled independently of others

Why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired

UDP: more

often used for streaming multimedia apps

loss tolerant

• rate sensitive

other UDP uses

o DNS

SNMP

reliable transfer over UDP: add reliability at application layer

> application-specific error recovery!

Length, in bytes of UDP segment, including header

32 bits	
source port #	dest port #
→length	checksum
Application	
data	
(message)	

22 6:44

UDP segment format

UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

Sender:


- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected. But maybe errors nonetheless? More later

Internet Checksum Example

- Note
 - When adding numbers, a carryout from the most significant bit needs to be added to the result
- Example: add two 16-bit integers




Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)


Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Reliable data transfer: getting started




Reliable data transfer: getting started

We'll:


- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
 - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver

state: when in this "state" next state uniquely determined by next event



Rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
 - o no bit errors
 - no loss of packets
- separate FSMs for sender, receiver:
 - sender sends data into underlying channel
 - o receiver read data from underlying channel



sender

receiver

Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
 - checksum to detect bit errors
- the question: how to recover from errors:
 - o acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
 - error detection
 - receiver feedback: control msgs (ACK,NAK) rcvr->sender

rdt2.0: FSM specification

rdt_send(data)
snkpkt = make_pkt(data, checksum)
udt_send(sndpkt)

Wait for
call from
above

rdt_rcv(rcvpkt) && isNAK(rcvpkt)

ACK or
NAK

rdt_send(sndpkt)

rdt_send(sndpkt)


rdt_send(sndpkt)

sender


receiver

rdt_rcv(rcvpkt) && corrupt(rcvpkt) udt send(NAK) Wait for call from below rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) extract(rcvpkt,data) deliver_data(data) udt_send(ACK)

rdt2.0: operation with no errors



rdt2.0: error scenario



rdt2.0 has a fatal flaw!

What happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


Handling duplicates:

- sender retransmits current pkt if ACK/NAK garbled
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt


stop and wait

Sender sends one packet, then waits for receiver response

rdt2.1: sender, handles garbled ACK/NAKs



rdt2.1: receiver, handles garbled ACK/NAKs



rdt2.1: discussion

Sender:

- seq # added to pkt
- \square two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must "remember" whether "current" pkt has 0 or 1 seq. #


Receiver:

- must check if received packet is duplicate
 - state indicates whether O or 1 is expected pkt seq#
- note: receiver can not know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- □ same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

rdt2.2: sender, receiver fragments




rdt3.0: channels with errors and loss


New assumption:

- underlying channel can also lose packets (data or ACKs)
 - checksum, seq. #, ACKs, retransmissions will be of help, but not enough
- Approach: sender waits "reasonable" amount of time for ACK
- retransmits if no ACK received in this time
- ☐ if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but use of seq. #'s already handles this
 - receiver must specify seq # of pkt being ACKed
- requires countdown timer


rdt3.0 sender




rdt3.0 in action



(a) operation with no loss



rdt3.0 in action



Performance of rdt3.0

- rdt3.0 works, but performance stinks
- □ ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$d_{trans} = \frac{L}{R} = \frac{8000 \text{bits}}{10^9 \text{bps}} = 8 \text{ microsecon ds}$$

O U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- 1KB pkt every 30 msec -> 33kB/sec thruput over 1 Gbps link
- network protocol limits use of physical resources!

rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yet-tobe-acknowledged pkts

- range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

Two generic forms of pipelined protocols: go-Back-N, selective repeat

Pipelining: increased utilization



Pipelining Protocols

Go-back-N: overview

- sender: up to N unACKed pkts in pipeline
- receiver: only sends cumulative ACKs
 - doesn't ACK pkt if there's a gap
- □ sender: has timer for oldest unACKed pkt
 - o if timer expires: retransmit all unACKed packets


Selective Repeat: overview

- sender: up to N unACKed packets in pipeline
- receiver: ACKs individual pkts
- sender: maintains timer for each unACKed pkt
 - o if timer expires: retransmit only unACKed packet

Go-Back-N

Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unACKed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
 - may receive duplicate ACKs (see receiver)
- timer for each in-flight pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window

GBN: sender extended FSM

```
rdt send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextsegnum])
                          if (base == nextseqnum)
                            start_timer
                          nextseqnum++
                       else
   Λ
                         refuse_data(data)
  base=1
  nextseqnum=1
                                           timeout
                                           start timer
                             Wait
                                           udt_send(sndpkt[base])
                                           udt send(sndpkt[base+1])
rdt_rcv(rcvpkt)
 && corrupt(rcvpkt)
                                           udt_send(sndpkt[nextsegnum-1])
                         rdt_rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop_timer
                          else
                           start_timer
```

GBN: receiver extended FSM




ACK-only: always send ACK for correctly-received pkt with highest in-order seq

- may generate duplicate ACKs
- o need only remember expectedseqnum

out-of-order pkt:

- discard (don't buffer) -> no receiver buffering!
- Re-ACK pkt with highest in-order seq #


<u>GBN in</u> action



Selective Repeat

- receiver individually acknowledges all correctly received pkts
 - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
 - sender timer for each unACKed pkt
- sender window
 - N consecutive seq #'s
 - again limits seq #s of sent, unACKed pkts

Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

Selective repeat

-sender

data from above:

if next available seq # in window, send pkt

timeout(n):

resend pkt n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

-receiver

pkt n in [rcvbase, rcvbase+N-1]

- \Box send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt


pkt n in [rcvbase-N,rcvbase-1]

 \Box ACK(n)

otherwise:

ignore


Selective repeat in action



Selective repeat: dilemma

Example:

- seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- incorrectly passes duplicate data as new in (a)
- Q: what relationship between seq # size and window size?



Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- ☐ 3.4 Principles of reliable data transfer


- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size
- send & receive buffers

- ☐ full duplex data:
 - bi-directional data flow in same connection
 - MSS: maximum segment size
- connection-oriented:
 - handshaking (exchange of control msgs) init's sender, receiver state before data exchange
- ☐ flow controlled:
 - sender will not overwhelm receiver



TCP segment structure


URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)

RST, SYN, FIN: connection estab (setup, teardown commands)

> Internet checksum' (as in UDP)



counting
by bytes
of data
(not segments!)

bytes rcvr willing to accept


TCP seq. #'s and ACKs

Seq. #'s:

byte stream "number" of first byte in segment's data

ACKs:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-of-order segments
 - A: TCP spec doesn't say, - up to implementer



simple telnet scenario

TCP Round Trip Time and Timeout

- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout
 - unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- □ SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT


TCP Round Trip Time and Timeout

```
EstimatedRTT = (1-\alpha)*EstimatedRTT + \alpha*SampleRTT
```

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- \Box typical value: $\alpha = 0.125$

Example RTT estimation:

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



TCP Round Trip Time and Timeout

Setting the timeout

- EstimtedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- ☐ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP reliable data transfer

- □ TCP creates rdt service on top of IP's unreliable service
- pipelined segments
- cumulative ACKs
- □ TCP uses single retransmission timer

- retransmissions are triggered by:
 - o timeout events
 - duplicate ACKs
- initially consider simplified TCP sender:
 - ignore duplicate ACKs
 - ignore flow control, congestion control

TCP sender events:

data rcvd from app:

- create segment with seq#
- □ seq # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unACKed segment)
- expiration interval:

TimeOutInterval

timeout:

- retransmit segment that caused timeout
- restart timer

ACK rcvd:

- □ if acknowledges previously unACKed segments
 - update what is known to be ACKed
 - o start timer if there are outstanding segments


```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
      create TCP segment with sequence number NextSeqNum
      if (timer currently not running)
         start timer
      pass segment to IP
      NextSeqNum = NextSeqNum + length(data)
   event: timer timeout
      retransmit not-yet-acknowledged segment with
           smallest sequence number
      start timer
   event: ACK received, with ACK field value of y
      if (y > SendBase) {
         SendBase = y
         if (there are currently not-yet-acknowledged segments)
              start timer
 } /* end of loop forever */
```

TCP sender (simplified)


Comment:

- SendBase-1: last cumulatively
 ACKed byte
 Example:
- SendBase-1 = 71;
 y= 73, so the rcvr
 wants 73+;
 y > SendBase, so
 that new data is
 ACKed

TCP: retransmission scenarios



TCP retransmission scenarios (more)



Cumulative ACK scenario


TCP ACK generation [RFC 1122, RFC 2581]

Event at Receiver	TCP Receiver action
Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
Arrival of in-order segment with expected seq #. One other segment has ACK pending	Immediately send single cumulative ACK, ACKing both in-order segments
Arrival of out-of-order segment higher-than-expect seq. # . Gap detected	Immediately send duplicate ACK, indicating seq. # of next expected byte
Arrival of segment that partially or completely fills gap	Immediate send ACK, provided that segment starts at lower end of gap

Fast Retransmit

- time-out period often relatively long:
 - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
 - o sender often sends many segments back-toback
 - if segment is lost, there will likely be many duplicate ACKs for that segment

- ☐ If sender receives 3 ACKs for same data, it assumes that segment after ACKed data was lost:
 - o fast retransmit: resend segment before timer expires



Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y
          if (y > SendBase) {
             SendBase = y
             if (there are currently not-yet-acknowledged segments)
                 start timer
          else {
               increment count of dup ACKs received for y
               if (count of dup ACKs received for y = 3) {
                  resend segment with sequence number y
```

a duplicate ACK for already ACKed segment

fast retransmit


Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP Flow Control

receive side of TCP connection has a receive buffer:




app process may be slow at reading from buffer

flow control

sender won't overflow receiver's buffer by transmitting too much, too fast

speed-matching service: matching send rate to receiving application's drain rate

TCP Flow control: how it works



(suppose TCP receiver discards out-of-order segments)

- unused buffer space:
- = rwnd

- receiver: advertises unused buffer space by including rwnd value in segment header
- sender: limits # of unACKed bytes to rwnd
 - guarantees receiver's buffer doesn't overflow

Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - o flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP Connection Management

- Recall: TCP sender, receiver establish "connection" before exchanging data segments
- initialize TCP variables:
 - o seq. #s
 - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator Socket clientSocket = new Socket ("hostname", "port number");
- server: contacted by client Socket connectionSocket = welcomeSocket.accept();

Three way handshake:

- Step 1: client host sends TCP SYN segment to server
 - specifies initial seq #
 - o no data
- Step 2: server host receives SYN, replies with SYNACK segment
 - server allocates buffers
 - specifies server initial seq.#
- Step 3: client receives SYNACK, replies with ACK segment, which may contain data


TCP Connection Management (cont.)

Closing a connection:

client closes socket:
 clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server

Step 2: server receives FIN, replies with ACK. Closes connection, sends FIN.




TCP Connection Management (cont.)

Step 3: client receives FIN, replies with ACK.


 Enters "timed wait" will respond with ACK to received FINs

Step 4: server, receives ACK. Connection closed.

Note: with small modification, can handle simultaneous FINs.



TCP Connection Management (cont)



Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer


- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control


Principles of Congestion Control


Congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- □ a top-10 problem!

- two senders, two receivers
- one router, infinite buffers
- no retransmission









- large delayswhen congested
- maximum achievable throughput

- one router, finite buffers
- sender retransmission of lost packet




- \square always: $\lambda_{in} = \lambda_{out}$ (goodput)
- "perfect" retransmission only when loss: $\chi' > \chi$ in out,
- \blacksquare retransmission of delayed (not lost) packet makes λ_{in} larger (than perfect case) for same λ




"costs" of congestion:

- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt

- four senders
- multihop paths
- timeout/retransmit





another "cost" of congestion:

□ when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Approaches towards congestion control

two broad approaches towards congestion control:

end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate sender should send at

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer


- □ 3.5 Connection-oriented transport: TCP
 - o segment structure
 - o reliable data transfer
 - flow control
 - connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

TCP congestion control:

- goal: TCP sender should transmit as fast as possible, but without congesting network
 - Q: how to find rate just below congestion level
- decentralized: each TCP sender sets its own rate, based on implicit feedback:
 - ACK: segment received (a good thing!), network not congested, so increase sending rate
 - lost segment: assume loss due to congested network, so decrease sending rate

TCP congestion control: bandwidth probing

- "probing for bandwidth": increase transmission rate on receipt of ACK, until eventually loss occurs, then decrease transmission rate
 - continue to increase on ACK, decrease on loss (since available bandwidth is changing, depending on other connections in network)



- Q: how fast to increase/decrease?
 - details to follow

TCP Congestion Control: details


sender limits rate by limiting number of unACKed bytes "in pipeline":

LastByteSent-LastByteAcked ≤ cwnd

- o cwnd: differs from rwnd (how, why?)
- o sender limited by min(cwnd, rwnd)
- roughly,

rate =
$$\frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

cwnd is dynamic function of perceived network congestion



TCP Congestion Control: more details

segment loss event: reducing cwnd


- □ timeout: no response from receiver
 - o cut cwnd to 1
- □ 3 duplicate ACKs: at least some segments getting through (recall fast retransmit)
 - o cut cwnd in half, less aggressively than on timeout

ACK received: increase cwnd

- □ slowstart phase:
 - increase exponentially fast (despite name) at connection start, or following timeout
- congestion avoidance:
 - o increase linearly

TCP Slow Start


- when connection begins, cwnd = 1 MSS
 - example: MSS = 500 bytes& RTT = 200 msec
 - initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
 - desirable to quickly ramp up to respectable rate
- increase rate exponentially until first loss event or when threshold reached
 - o double cwnd every RTT
 - done by incrementing cwnd
 by 1 for every ACK received



Transitioning into/out of slowstart

ssthresh: cwnd threshold maintained by TCP

- on loss event: set ssthresh to cwnd/2
 - o remember (half of) TCP rate when congestion last occurred
- when cwnd >= ssthresh: transition from slowstart to congestion avoidance phase



TCP: congestion avoidance

- when cwnd > ssthresh grow cwnd linearly
 - o increase cwnd by 1 MSS per RTT
 - o approach possible congestion slower than in slowstart
 - o implementation:


```
cwnd = cwnd + MSS*
MSS/cwnd for each ACK
received
```

AIMD


- ACKs: increase cwnd by 1 MSS per RTT: additive increase
- loss: cut cwnd in half (non-timeout-detected loss): multiplicative decrease

AIMD: Additive Increase Multiplicative Decrease


TCP congestion control FSM: overview



TCP congestion control FSM: details



Popular "flavors" of TCP



Summary: TCP Congestion Control

- when cwnd < ssthresh, sender in slow-start phase, window grows exponentially.
- when cwnd >= ssthresh, sender is in congestionavoidance phase, window grows linearly.
- □ when triple duplicate ACK occurs, ssthresh set to cwnd/2, cwnd set to ~ ssthresh
- when timeout occurs, ssthresh set to cwnd/2, cwnd set to 1 MSS.

TCP throughput

- □ Q: what's average throughout of TCP as function of window size, RTT?
 - o ignoring slow start
- □ let W be window size when loss occurs.
 - owhen window is W, throughput is W/RTT
 - just after loss, window drops to W/2, throughput to W/2RTT.
 - oaverage throughout: .75 W/RTT

TCP Futures: TCP over "long, fat pipes"


- example: 1500 byte segments, 100ms RTT, want 10
 Gbps throughput
- requires window size W = 83,333 in-flight segments
- throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- \Box \rightarrow L = 2·10⁻¹⁰ Wow
- new versions of TCP for high-speed

TCP Fairness


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

Two competing sessions:

- Additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - pump audio/video at constant rate, tolerate packet loss

Fairness and parallel TCP connections

- nothing prevents app from opening parallel connections between 2 hosts.
- web browsers do this
- example: link of rate R supporting 9 connections;
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2!

Chapter 3: Summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - o reliable data transfer
 - o flow control
 - congestion control
- instantiation and implementation in the Internet
 - o UDP
 - TCP

Next:

- □ leaving the network "edge" (application, transport layers)
- □ into the network "core"